

# 7

## Version Information

### 7.1 Available AIR Connect Versions

There are multiple versions available in the field. The following table shows the main differences. Please note that any AIR Connect unit in the field can have any software version.

The most critical difference between the different versions is the IP address. It is recommended to either make the IP-Address user configurable or to implement automatic detection (i.e. to try all different possibilities in software).

	2012 Version	2013-2014 Version	2014-2018 Version	Current Version
<b>Module SSID</b>	WIFLY-GSX	WIFLY-EZX	AIR Connect	AIR Connect
<b>IP-Address</b>	169.254.1.1	1.2.3.4	192.168.1.1	192.168.1.1
<b>Network Mode</b>	Ad-Hoc	Soft AccessPoint	AccessPoint	AccessPoint
<b>PIN Code</b>	Required	Required	Required	-
<b>Network Security</b>	-	-	-	Printed on enclosure
<b>Serial Number</b>	from B104-1001	From B104-1101	From B104-1584	from 3D672F (HEX)

The four-digit PIN-CODE used in all versions up to 2018 is always calculated by adding the number 3642 to the device's serial number. Therefore individual device serial numbers may be calculated from the pin-code entered by the user.